

APPLICATION NOTE


MAESTRO FIRMWARE UPDATE PROCEDURE



ALWAYS KEEP YOUR MAESTRO UP TO DATE
TO TAKE ADVANTAGE OF ALL THE NEW
FUNCTIONALITIES


FOLLOW THIS EASY STEP-BY-STEP UPDATE PROCEDURE

1. Download the update file from the website at:
<http://gentec-eo.com/downloads/software-firmware> in the **Firmware** tab
2. Save it to a known location on your PC (like your desktop)
3. Unzip the file:
 - 3.1 Locate the ZIP file on your computer
 - 3.2 Right-click on it and choose "Extract All..."
 - 3.3 Follow the instructions on the screen
 - 3.4 Locate the extracted folder and open it
 - 3.5 You should now see the BIN file



APPLICATION NOTE

- Copy the BIN file on a USB key, directly in the main folder (not in a sub-folder)



- Plug the USB key in the MAESTRO

- Go to **HOME** 

- About** 

- Press the **Update** button 

- Wait for the MAESTRO to do the update sequence

- When the reboot message appears, turn off the MAESTRO

- Wait a few seconds

- Turn it on again and the update will be done

- If you want to check the update has been done, go in **HOME** – **About** again and verify that the firmware version corresponds to the initial update file